

Linux and PF firewalls commands cheat sheet

Firewalld daemon management (Red Hat based distributions)

Table 1. firewall-cmd commands

Command	Description
firewall-cmd --state	Show firewall daemon status
firewall-cmd --list-all	List currently active rules
firewall-cmd --reload	Reload firewall keeping the state table. Active sessions do not disconnect. On finishing reload will output success .
firewall-cmd --get-default-zone	Show the default zone for interfaces.
firewall-cmd --get-zones	List all available zones
firewall-cmd --get-active-zones	Show active zones, including to which zone each interface belongs.
firewall-cmd --list-all-zones	List all zones with their rules and associated interfaces.
firewall-cmd -add-service <service name>	Add predefined service by name to the default zone, with action ACCEPT, e.g. firewall-cmd -add -service ftp .

Ubuntu Uncomplicated Firewall (ufw)

Table 2. ufw management commands

Command	Description
ufw status	Show whether the firewall is on and if on, list the active rules.
ufw enable	Enable firewall.
ufw disable	Disable firewall
ufw reload	Reload firewall and rules.
ufw allow <predefined service name>	Allow some service in any direction from/to any IP address using so called simple rule syntax. The service names are as per /etc/services . E.g. to allow ssh from any: ufw allow ssh .

Command	Description
<code>/etc/ufw/before.rules</code>	Some rules are pre-allowed by default, to change them edit this file and reload the firewall.

PF (Packet Filter) management for FreeBSD & OpenBSD

Command	Description
<code>pfctl -d</code>	Disable PF in place, does not survive reboot.
<code>pfctl -ef /etc/pf.conf</code>	Enable PF and load the rule set from file <code>/etc/pf.conf</code> in one go.
<code>pfctl -nf /etc/pf.conf</code>	Parse security rules stored in a file without installing them (dry run).
<code>pass in quick on egress from 62.13.77.141 to any</code>	'Quick' rule (means allows this traffic on all interfaces, otherwise we would need 2nd rule allowing this traffic in <i>outgoing</i> direction on egress interface) to allow incoming ANY port/protocol with the source being <code>62.13.77.141</code> and destination being ANY IP address behind the PF firewall. NOTE: here, <code>egress</code> is not a direction, but a group name to which the interface in question (<code>em0</code>) belongs to. In OpenBSD you set it in a file <code>/etc/hostname.em0: group egress</code> or in real-time with the command: <code>ifconfig em0 group egress</code> .